- p. 85 Commands at top of screen or in LIMA are not processed unless ENTER is hit
- 27 Arrows move cursor up/down/left/right
 SHIFT up-arrow goes to command line
 SHIFT down-arrow goes to next line
 SHIFT left-arrow goes to left margin
 or into LIMA (only way to LIMA)
 SHIFT right-arrow goes to end of line
 or to next line if at end line.
- The "CLEAR" key is NEWSCRIPT's CONTROL key. It may be held down or touched once for a one-stroke lock. While active, these keys do this:
- 33 B Back-scroll one screen
- 30 Delete character at cursor
- 33 E go to End of file
- 33 F Forward-scroll one screen
- 88 H show the HELP menu
- 30 I toggle Insert-char. mode
- N move screen to Next line
- 88 P toggle Playback of tape
- 34 S Save file to disk
- 33 T. go to Top of file
- 33 U move screen Up one line
- 30 W delete Word at cursor
- 88 X perform current X command
- 88 Y perform current Y command
- re-execute last "LOCATE"
- move screen 20 to the right (see
- move screen 20 to the left "HO")
- 88 BREAK break line at cursor
- 88 SPACE blank line from cursor
- 88 displays the left bracket
 - (Model 3, or up-arrow Model I)
- 124578 toggle screen graphics blocks



9/82

Copyright (c) 1982, TTSC RELEASE 7.0

NEWSCRIPT TEXT EDITOR 2 of 3

29 Shift-zero toggles lower-case.

89

89

90

91

124

114

SHIFT-CLEAR, followed by any of:

89 r toggles auto-Repeat of keys

p does a screen Print

90 v routes most Video to printer

as well as to video

01-ff hexadecimal values

minus gives an underscore

arrows, shifted arrows give special

characters (experiment!)

To cancel CLEAR or SHIFT-CLEAR, just hit same key(s) a second time.

CANCELLING ERRORS

(all on command line)

122 Whoops discards changes on screen

116 QUit discards changes in memory

SCREEN MOVEMENT (SCROLLING COMMANDS)

98 Back 119 Up 119 Top 120 View n,n

107 Forward 103 Down 98 BOttom 120 View ± n

115 Next 120 View *

110 HOrizontal n

.A .B .C

SEARCHING FOR TEXT (WITHIN LINES)

113 Locate /string/

113 /string short for 'locate'

-string short for 'locate-not'

106 Find text column-dependent search

Zone n,n restrict search columns

109 GRid ON/OFF column marker aid

114 Locate UP /string/

BLOCK MANIPULATION

(FULL LINES ONLY)

Move .B 101 COpy .B 102 DElete .B

114 Move .C 101 COpy .C 104 DString/to here/

111 Join 111 Join b

CHANGING TEXT GLOBALLY

99 Change /string1/string2/ n * #

96 Alter /c/a/ n * (char/ascii)

117 Replace line-of-text

98 BReak /line at this string/

106 FLow ON or OFF for autosplit

INSERTING LINES OF TEXT

111 I line-of-text

111 I (gives 12 new lines)

STring n,c ('n' occurrences of 'c'

DELETING LINES OF TEXT

DElete n delete 'n' lines

DString /from cursor to here/

DElete .B (block .A thru .B)

FILES ('n' stands for a number)

117 SAve 104 END 103 DIR n

117 SAve fileid 104 END fileid 112 KILL id

117 SAve:n 116 QUit 115 NAme id

108 GET fileid 102 DBlanks 97 AUto n

115 PUT fileid

MACROS (Commands that use other cmnds)

122-123 X, Y, XY

125 = repeat last command

re-display last command

125 & execute and retain this command

STATUS OF THE EDITOR AND TEXT

107 FRee 110 HArdcopy 120 View

112 LEngth 115 NAme 97 AUto

91 LIMA (access via SHIFT left-arrow)

Dn delete 'n' lines

In inserts 'n' blank lines

Rn repeats line 'n' times

moves line to top of screen

.A .B .C three named points

```
MARGINS
                    left margin adjustment
     .AD
          5
129
                    line length (1/10 inches)
     .LL
          65
149
             (the right margin is whatever is
             leftover after adding .AD + .LL)
                    left margin (same as .AD)
     .LM
           6
150
                    top margin (# lines)
     .TM
           6
172
                    bottom margin
     .BM
          6
131
                    page length (# lines)
           66
     .PL
154
            (the body of the text is PL-TM-BM)
                    heading space for title
     .HS
142
                    heading margin below title
     .HM
140
                    footing space for title
     .FS 1
140
                    footing margin above title
     .FM
138
                    logo space on first page
     .LS
151
     RIGHT JUSTIFICATION
52
                     justify (ON, OFF, RIGHT)
           ON
     JU.
147
                     combine lines (ON, OFF)
     .CO
           ON
135
                     (JU and CO: ON or OFF)
           ON
     .FO
139
      INDENTATION
50
                     indent (1/10 inches)
     .IN
           0
145
                     automatic hanging indent
     .HI
           0
140
                     manual offset (like .HI)
     .OF
           0
152
                     point/paragraph numbering
     .PT
           n
157
                     center (ON, OFF, or 'n')
      .CE
           1
134
                     start new paragraph**
      .PP
           3,2,5,0
155
                     tab column settings **
      .TB
           & 1,5,10
169
      PITCH, FONT, AND TYPEFACE
54
                     begin font (10, 12, 16, 737)
           10
      .BF
130
                     microspacing controls
           1,0
      .SD
164
                     disk-resident width table
           fileid
      .TR
172
      MINI-EDIT MODE (nothing saved to disk)
82
                     use current line as-is
      -enter-
                     delete current line
      D
                     replace current line
      R
           text
                     insert text above line
           text
```

terminate mini-edit mode

T

TITLES (all have/left/center/right/)

174 .TT /1/c/r/ top title**

bottom title**

.OT odd-page top title**

even-page top title**

.OB odd-page bottom title**

137 .EB even-page bottom title**

156 .PS \$ page number symbol in title

155 .PN ON auto page number (ON, OFF)

SPACING BETWEEN LINES

.SP 1 space 'n' lines, always

167 .SK 1 space 'n' lines if not at top

153 .PA n start new page, 'n' optional

131 .BR start new print line

135 .CP n conditional new page

137 .DS start double spacing

168 .SS start single-spacing

166 .SH $\pm n$ half-space lines (- up)

149 .Ll n lines per inch (6 or 8)

FILES

50

.AP fileid append/switch to 'fileid'**

.IM fileid imbed 'fileid' into text**

158 .RD c,file read N&A into form letters**

168 .ST msg stop to change disk/wheel**

.TC text table of contents entry **

146 .IX text index entry**

MISCELLANEOUS

.CM msg comment (not printed)**

DA 0,1,2,3 darkness (boldface lines)

137 .ES! redefine escape character

142 .HY \ conditional hypenation

148 .KE keyboard entry of text **

172 .TR i,j,k translate char. values

176 .US text underscore 'text'**

^{**}these control words must be last on a line.

Additional ones are ignored.

ESCAPE SEQUENCES WITHIN TEXT[†]

!\$!% start/stop underlining

59 !(!) start/stop double-width

67 !/ !? start/stop italics

58

59

67

128.1

!>

PA

67 !* !: start/stop boldface

forward 1/2 space (subscript)

backward 1/2 space (superscript)

cancel sub/superscripts†

67 !< backspace 1 position

(tescape sequences are printerindependent, but not all of

them work with all printers)

pause printer here

RUN-TIME OPTIONS

output only to Video V stop at end of each page ST activate mini-edit mode ED specify range of pages to print PG double-space all printing DS triple-space all printing TS number of multiple copies CC print each fileid in margin ID ' print all lines dark (boldface) DA number all lines in left margin NU only print Table of Contents TC ignore ".TC" and ".IX" entries NT ignore ".AP" (no append) NA

number to place on first page

OTHER SCRIPT FACILITIES

- Several control words can go on one line if separated by semi-colons, subject to restrictions of words that must be last on the line
- To display the Directory when asked for a Filename, reply question mark and a number, such as: ?1
- To interrupt printing, press ENTER. To pause Video output: SHIFT@ (Press any key to resume)